



MNWIN HELP AND MANUAL

© 2006 Custom Software Solutions

Maintenance Help Document MNWIN 32 Transportation Management Software

by BJ Exum


Special Thanks to Diane Harper for
the original help files.

Custom Software Solutions
Carbondale, Illinois
(618)549-5550
www.tmshome.com

Table of Contents

Foreword	0
Part I Trucks	1
Part II Trailers	1
Part III Vehicles	2
Part IV Vehicle Types	3
Index	5

1 Trucks




ID	DESC	LEASOR	YEAR	S	ENG_MOD	TRCKPM	LSPDMTR
102	FREIGHTLINER	CUSTOM SOFTWARE	1993	P	SERIES60	Y	12100.0
103	FREIGHTLINER	CUSTOM SOFTWARE	1996	A	SERIES60	Y	60000.0
104	FREIGHTLINER	CUSTOM SOFTWARE	1996	P	SERIES60	Y	10000.0
106	FREIGHTLINER	CUSTOM SOFTWARE	1995	A	SERIES60	Y	80000.0
109	FREIGHTLINER	CUSTOM SOFTWARE	1996	A		Y	44000.0
110	FREIGHTLINER	CUSTOM SOFTWARE	1996	A	SERIES60	Y	368740.0
112	FREIGHTLINER	CUSTOM SOFTWARE	1998	E		Y	11111.0
118	FREIGHTLINER	CUSTOM SOFTWARE	1997	E		Y	3654.0
132	FREIGHTLINER	CUSTOM SOFTWARE	1997	A		N	35687.0
133	FREIGHTLINER	CUSTOM SOFTWARE	1998	A		Y	30000.0
140	FREIGHTLINER	CUSTOM SOFTWARE	1998	A		Y	60000.0

Your most important buttons for trucks and trailers will probably be the pending PM and the history buttons. You will find them to be helpful tools for tracking.

When a unit is no longer in service you enter the ending service date and put an "I" in status. This will remove the unit from the active screen (as long as ending service date is not same date as today's date). To view these inactive units, press the SHOW ALL button.

2 Trailers



ID	DESC	LEASOR	YEAR	LENGTH	S
57108	86/HOBBS 49503			57	A
57123	86/HOBBS 49517			57	P
57126	86/HOBBS 49520			57	A
57194	89/STRICK 03691			57	A
57206	89/STRICK 03703			57	P
57275	90/NATIONAL 41958			57	P
57286	90/NATIONAL 41969			57	P
57412	96/WABASH 85194			57	H
57413	96/WABASH 85195			57	A
57464	96/WABASH 85246			57	A
57467	96/WABASH 85249			57	H

Your most important buttons for trucks and trailers will probably be the pending PM and the history buttons. You will find them to be helpful tools for tracking.

When a unit is no longer in service you enter the ending service date and put an "I" in status. This will remove the unit from the active screen (as long as ending service date is not same date as today's date). To view these inactive units, press the SHOW ALL button.

3 Vehicles

Vehicles/Equipment Master File

There are two places available to enter/edit your Trucks, Trailers, and Vehicles. This equipment is listed on both the Operations menu and the Setup menu

A Vehicle in MNWIN is defined as any equipment on which you perform maintenance. This includes trucks, trailers, company cars, pickups, tractors, fork-lifts, etc.

As in other support files, in addition to the buttons, F4 adds new records, F2 edits existing records, and F3 deletes existing records. Deletions should only be done if NO actions have been taken with the vehicle. Instead, making units inactive is suggested. The F1 key lists records on file.

MNWIN categorizes equipment by using the Vehicle Type field. This field allows you to group vehicles of the same type. For example, all cars in your fleet could have the vehicle Type of "CAR". All pickup trucks could have the unit type of "PICKUP". The vehicle type field has ten characters for this purpose.

Equipment that is to be shared with other CSS/TMS modules (such as DPWIN) MUST be identified as FLT TRUCK or FLT TRAIL either by typing in words exactly as they are above, or using the F1 key and option 1 or 2. These unit types are the only types accessible by other programs.


Equipment is individualized using the Unit ID field. The Unit ID is used to assign a unique number to each unit under that unit type. For example, units with the type of "PICKUP" could be designated as unit number "1", "2", "3", etc. Four characters are available to use for unit number, unless the unit number has been expanded.

OUTSIDE WORK - It is recommended to add a unit type of OUTSIDE for work done for individuals not a part of the normal system. Owner operators

whose trucks are used in the CSS/TMS Dispatch system should have their vehicles included in FLT TRUCK, but for those who are not a part of Dispatch should be identified as OUTSIDE, and at least one vehicle entered for each customer for whom you do work and send invoices.

If the system is not linked to any other CSS/TMS modules, the unit number field can be expanded in the configuration screens, but **ONLY** if other modules are not present. If you are linked to other CSS/TMS modules the Equipment ID settings **MUST** match in each program. This is handled in System Set up and should be done by CSS Support, due to possible file conversions.

4 Vehicle Types



D	Vehicle Type	Description
	CARS	COMPANY CARS
	FLT TRAIL	Trailer File Vehicles
	FLT TRUCK	Truck File Vehicles
	SHOP MISC	MISC YARD AND SHOP VEHICLES

Edit-F2 Delete-F3 Add-F4

MNWIN categorizes equipment by using the Vehicle Type field. This field allows you to group vehicles of the same type. For example, all cars in your fleet could have the vehicle Type of "CAR". All pickup trucks could have the unit type of "PICKUP". The vehicle type field has ten characters for this purpose.

Index

- v -

vehicles/Equipment Master File 2